


Add the intuiface application to zebrix:


Intuiface is a third-party application that allows you to create presentations or mini wysiwig sites (without code) using the tactile capacity of screens. You create your content on the intuiface application outside zebrix and integrate the link obtained at the end of the design process into a zebrix page.

An intuiface link is required: <https://web.intuiface.com/intuiface-overview> (example of a link that can be used)


Click on the page tab :




Then press + New :



Then choose the type of page you want to create (new blank page) :




Then choose the name of your page :




Congratulations, you've just created a new page.

Now you need to add a zone that will contain your intuitive page. To do this, first add a zone to your page.

Click on the + button in the zone box on the right of your screen .:



A zone can host different functions (text, image, video, etc.), but here we need a web zone to display an external iframe. To do this, we're going to click on the **zone type selection** drop-down menu, and choose **web** :



Translated with DeepL.com (free version)

From: <https://documentation.zebrix.net/> - **zebrix documentation**

Permanent link: https://documentation.zebrix.net/doku.php?id=en:ajouter_une_page_intuiface&rev=1721035897

Last update: **2024/07/15 11:31**

